

SLHOSTING - DIRECTADMIN AUTENTICAZIONE A DUE FATTORI (2FA)

L'autenticazione a due fattori (2FA) è un metodo di riconoscimento che si basa sull'utilizzo congiunto di due metodi di autenticazione individuali.

Il metodo di autenticazione a due fattori consente di proteggere l'accesso al Server/Pannello di Controllo riducendo i rischi legati, ad esempio, al furto di password.

Che cosa serve:

1. Un'applicazione di autenticazione a due fattori 2FA installata sullo smartphone (come Google Authenticator, Microsoft Authenticator, o simili)
2. Gli accessi al pannello di controllo.

Procedura per attivare autenticazione a due fattori

Per attivare il metodo di autenticazione a due fattori è necessario accedere all'interfaccia del server che ospita il nostro piano hosting alla solita pagina con la logica <https://lnxX.slhosting.it:2087>

Inserire le credenziali di accesso in vostro possesso.

Una volta connesso all'interfaccia di gestione cliccare su "Strumenti" e nel menù a tendina selezionare "Autenticazione a due fattori"

Used	
Disk Space (mb)	177990
Bandwidth (gb)	4.0785
Domains	204
Users	169
Resellers	2

Nella pagina che si apre cliccare su "two step authentication"

The screenshot shows the SLHOSTING user interface. At the top left is the SLHOSTING logo. Below it is a navigation bar with icons for Home, Webmail, Password, Help, Files, and Logout. The main content area features a 'Change your Password' form with the following fields and options:

- Current DirectAdmin Password: [masked]
- Enter Password: [input field]
- Re-Enter Password: [input field]
- DirectAdmin Account:
- Main FTP Account:
- Main Database Account:
- Submit button

Below the form is a link for 'Manage Security Questions' and a sub-link for 'Two-Step Authentication'. On the right side, there is a sidebar with 'Access Levels' (Admin, Reseller, User) and 'Your Account' details:

	Used	Max
Disk Space (MB)	4296.9	unlim
Bandwidth (GB)	0.0000	unlim
E-Mails	1	unlim
Ftp Accounts	1	unlim
Databases	0	unlim
Inodes	5544	unlim

Nella pagina successiva cliccare su "New secret"

The screenshot shows the 'Two-Step Authentication' settings page. It includes the following text:

Two-Step Authentication

To use this feature, download the Google Authenticator App for your phone (or equivalent), and scan in the QR code. The App will show you a code, which you'll use to Login to DirectAdmin. Scratch Codes are one-time use codes in case you don't have your phone, so keep them safe.

This feature is not turned on.
Create a new secret to begin.

Settings


- Secret: Note: Creating a new secret voids your current codes. Re-Scan the QR code and re-print your scratch codes.
- Description:
- Require valid Two-Step Authentication Code to login to this account.
- Allow API logins with the current User/password. Login Keys and Session Keys are always allowed.
- Notify me on all incorrect codes entries. Disabling this option will still notify you after 5 failed attempts.

Save button

Inquadrare il QRCode proposto, utilizzando un'applicazione apposita installata sullo smartphone



Tornare su password



Cliccare nuovamente su "two step authentication"

The screenshot shows the SLHOSTING control panel. At the top, there is a navigation bar with icons for Home, Webmail, Password, Help, Files, and Logout. Below this is a "Change your Password" form with fields for "Current DirectAdmin Password", "Enter Password", and "Re-Enter Password". There are also checkboxes for "DirectAdmin Account", "Main FTP Account", and "Main Database Account", all of which are checked. A "Submit" button is at the bottom of the form. To the right, there is a "Your Account" section with a table of usage statistics.

	Used	Max
Disk Space (MB)	4296.9	unlim
Bandwidth (GB)	0.0000	unlim
E-Mails	1	unlim
Ftp Accounts	1	unlim
Databases	0	unlim
Inodes	5544	unlim

Nella pagina successiva Inserire il codice e abilitare la voce "Richiedi un codice di autenticazione a due fattori valido per accedere a questo account"

The screenshot shows the SLHOSTING control panel interface. At the top, there is a navigation bar with icons for Home, Webmail, Password, Help, Files, and Logout. Below this, the 'Two-Step Authentication' section is active. It contains instructions on how to use the feature, a note that the feature is not turned on, and a 'Settings' section. The 'Settings' section includes a 'Secret' field with the value 'QC2Q 6IU5 YVBG EFMB' and a 'New Secret' button. A note states: 'Note: Creating a new secret voids your current codes. Re-Scan the QR code and re-print your scratch codes.' Below this is a 'QR Code' section with a large QR code and a 'Scan this code into your phone.' instruction. To the right of the QR code is a 'Before logging out, test your phone's code:' section with a '6 digit code' input field and a 'Test code' button. The 'Description' field contains 'admin@lnx7.slhosting.it'. At the bottom of the settings section, there are three checkboxes: 'Require valid Two-Step Authentication Code to login to this account.' (unchecked), 'Allow API logins with the current User/password. Login Keys and Session Keys are always allowed.' (checked), and 'Notify me on all incorrect codes entries. Disabling this option will still notify you after 5 failed attempts.' (checked). A 'Salva' button is located at the bottom right of the settings section.

Cliccare su "salva" per abilitare le modifiche.